


ODOT v2024 Workspace and Configuration Read Me

The ODOT workspace and configuration for Bentley MicroStation and OpenX software v2024 may be copied from the ODOT FTP Site using Windows File Explorer. *Copy and paste this link (ftp://ftp.odot.state.or.us/isb/appeng/ODOT_workspace/) into File Explorer; Chrome and Edge browsers do not work well with FTP.* Copy “v2024_External_ODOT.zip” and paste it to your own computer. Follow the instructions below.

Extract ODOT’s WorkSpace and Configure Your Software

Bentley’s ConfigurationSetup.cfg file that is provided in each application is used by ODOT to point to ODOT’s custom configuration that resides on your computer in C:\ODOT\v2024. We recommend that the most efficient method of using ODOT’s workspace is to extract the workspace to the C: drive and to configure your software to enable it to access that custom configuration following the steps below.

1. Extract “v2024_External_ODOT.zip” to C:\. This will create the ODOT folder structure, resulting in C:\ODOT\v2024 as shown below.



2. This step is only required to access the OregonDOT WorkSpace with data stored locally (not in ProjectWise). The ConfigurationSetup.ODOTcfg file in C:\ODOT\v2024 folder should be used to overwrite the ConfigurationSetup.cfg in the Configuration folder of installed Bentley CAD products:

C:\ProgramData\Bentley\MicroStation 2024\Configuration
C:\ProgramData\Bentley\OpenRoads Designer 2024.00\Configuration
C:\ProgramData\Bentley\OpenSite Designer 2024.00\Configuration
C:\ProgramData\Bentley\OpenBridge Modeler 2024.00\Configuration


You may wish to copy the original ConfigurationSetup.cfg file to ConfigurationSetup - Copy.cfg, so that you can restore the out of the box configuration.

To access ODOT’s workspace, you must change the name of the file that is provided in the ZIP file so that it exactly matches the name of the file in the product Configuration folder! Rename ConfigurationSetup.ODOTcfg to ConfigurationSetup.cfg – by removing ODOT from the name; then copy and paste the file into the Configuration folder, overwriting Bentley’s default file.

ODOT's ConfigurationSetup.cfg file points to the WorkspaceSetup.cfg file in C:\ODOT\v2024 and will display OregonDOT as the Workspace in the **Custom Configuration**.

Opening a Bentley CAD Application to use ODOT's workspace

1. Launch a Bentley CAD application from a desktop shortcut and select Custom Configuration from the dark blue band on the upper left side of the Work Page.



2. Select OregonDOT | ODOT Workspace-WorkSet couplet.
3. [Browse] to data or create a [New File] from an ODOT DGN seed.

About WorkSets

The WorkspaceSetup.cfg in the extracted v2024 folder is correctly configured to use the OregonDOT Workspace in C:\ODOT\v2024. OregonDOT points the MY_WORKSET_LOCATION to the local C: drive and provides a WorkSet folder structure and an empty "ODOT" WorkSet in C:\ODOT\CAD_Projects\Worksets\.

All ODOT resources are provided at the Organization level in C:\ODOT\v2024\Organization-Civil\ODOT_Standards. Only the default Sheet Index is provided via the WorkSet template; the default WorkSet Standards folder structure is intentionally empty.

Updates

Periodically, updates to the configuration will be published to deliver the latest resource files. When notified of an update you should extract the latest version of the "v2024_External_ODOT.zip" file to C: and overwrite the contents of C:\ODOT\v2024\ . Most of our updates will be to files in the Organization-Civil\ODOT_Standards\ folder.

Using ProjectWise with MicroStation and OpenX

- To use the OregonDOT Workspace when opening DGN documents in ProjectWise, it will be necessary to have previously downloaded the ODOT workspace and extracted it as described above. When using Bentley Applications integrated with ProjectWise Explorer and accessing PW_ODOT_PROD, your software's ConfigurationSetup.cfg file will not be used at all. If using ProjectWise Explorer, it is only necessary to have the workspace that is matched to your CADD software version present in C:\ODOT\.

- ProjectWise work areas are identified in PW_ODOT_PROD as CONNECT projects by setting a Project Attribute named Design Platform to a value of CONNECT.
- CONNECT work areas use a ProjectWise Configuration Settings Block to manage the configuration when a Bentley CADD product is used to open a DGN document.
- To open DGN documents in a CONNECT work area in ProjectWise, right-click on the DGN, use **Open With...** and select a Bentley CAD product from the “Open document with” dialog.
- When creating PDFs or printing using ProjectWise, use Apply Print Styles, as these are loaded at launch through a DGNLIB. If you need to search for a different pen table, click [Cancel] on the ProjectWise “Open Pen Table” dialog and select a pen table in a Windows “Open Pen Table” dialog, which will locate the standard pen tables from the local workspace without further navigation.

Accessing Other Resources When Using ProjectWise

DGN seed files are stored in ProjectWise in Documents\CAD_Resources\Seed and are also stored in the local configuration in C:\ODOT\v2024\Organization-Civil\ODOT_Standards\Seed. When using the ProjectWise Explorer, it is recommended to create new DGN files in your project without a Bentley CADD application open by using the ProjectWise>Document>New Document command.

Standard references are stored in the local configuration in C:\ODOT\v2024\Organization-Civil\ODOT_Standards\ref and can be accessed using the Directory History button after using the Attach Reference command. If the active DGN file is open from ProjectWise, you will need to [Cancel] out of the ProjectWise “Open” dialog and may use the Directory History icon on the Windows “Open” dialog in the upper right corner.

Current Platform as of September 2, 2025

ODOT is using this configuration with:

MicroStation (v24.00.02.062)

OpenRoads Designer (v24.00.02.025)

OpenSite Designer (v24.00.02.025)

OpenBridge Modeler (v24.00.02.022)

Bentley View (v24.00.02.023)

ProjectWise Explorer Client (v10.00.03.453)

Windows 11 (64-bit)

The configuration is maintained by the Engineering Applications Support Team ([EAST](#)).

Additional Resources

User Guides and other training materials are available on the [EAST Web Site](#).

Descriptions of the workspace components are on the [ODOT Workspace](#) page. The recent workspace updates are explained in a PDF with plain language and images.

Questions

If you have questions or to be placed on an e-mail distribution list to obtain notification of future updates, please contact EAST at ODOT.EAST@odot.oregon.gov.