

Cell Counting Reports

There are two ODOT reports available to count cells using MicroStation programs.


To create a report, Open the Reports dialog on the Ribbon: Drawing > Analyze > Reports > Reports.

Select a report. There is no need to expand the report.

- Cell Count - Model
- Cell Count - Selection

Make an element selection if needed.

Click the **Preview results** button to see a list of the counted cells. The next button to the right is **Place as Table** into the current model. To the right of that is **Export results** to Excel or a .CSV file.



Example Preview Results Report


Count	Cell Name
1	POLSIG
4	SIGNPB
6	SIGNPOST
3	SIGNPOSTPR
2	SIGNPR

COUNT (Count)	Cell Name
16	

Advanced Tip – Named Groups

If you need precise control of the which cells are counted, you can create a named group to define the selection. You do need to be familiar with Named Groups before trying to use the tool.

Named Groups is located on the Ribbon: Drawing > Home > Groups dialog launcher



Click **Select Elements in Named Group** to set the current selection set when counting.

